

POS Installation

Document: 1.2

POS: 5.8.3


DON: 3.6.9

PM: 6.13.16


1: Configure DON and POS

1.1: Load POS on browser get link from your mail



1.2: Here we have **Download DON** option this will download the new application once downloaded you need to install and open it



1.3: After installation you can open the software from desktop and you'll see this page. Here you have to give the license key which we have got from SAAS manager. After giving the license ID click on the **ACTIVATE** button.






1.4: Now you can this page here under **Wi-Fi** (interface) **you can see the IP** you have give this same IP in the POS DON configuration page




1.5: After giving the IP click the configure button


1.6: During that time you might get this error. If so go to site settings and enable insecure contents allow



1.7: Now, Allow this insecure content



Now click the configure button then you'll be redirected to login page




1.8: Here use the login info which you have created in the admin panel. After giving the authorised login you'll logged into POS page successfully

POS & Printer Manager Installation

2: Configure Printer manager and POS

2.1: After successfully configuring the POS & DON-Server then you need to proceed with the configuring the **PRINTER-MANAGER** with the below steps

Go to setting page in POS




2.2: Now in the settings page you can printer-manager options there you can see the download option you need to click. Then the printer-manager zip file will be downloaded.

2.3: Unzip file then open .exe file(installer)

2.4: After installation complete close installer then you can find printer manager shortcut on desktop and open it.

2.5: Give name as main-system or your preferred name, Then select system config type main-system or sub system (Each shop must have only one main-system others are sub-system)




2.6: Add system printer

2.6.1: Click **system printer** button. A modal will be opened, Then give printer name same as defined in admin panel and modal of printer.

2.6.2: Then select template (you can select from default template or you can create custom template from settings)


2.6.3: Select a printer from the system dropdown. It will display all printers already configured on the system. Then click add printer button.

2.6.4: Once printer is added in the list click on the the 3 dot icon use the printer button to take the test printer and verify for the reference



2.7: Add IP printer

Same as system printer instead of select printer from system dropdown. Need to enter IP.



2.8: Connect POS with printer manager

2.8.1: Create access code from printer manager -> settings -> white list -> new, Then enter user name and create.

2.8.2: Copy create access code enter on POS -> settings -> Printer manager -> Configure -> access code and enter IP address of printer manager installed system, Then configure



NOTE: If Android app needed you can also see the download button next to QR code button there on click download button POS for android will be downloaded.